

Timing a Show

To start timing a Producer with Approver status opens the Rundown properties by selecting **Rundown rover** → **Properties** or double-click the title bar of the Rundown.

5 PM News [12/04/2008 16:46]

Page	Story Slug	Segment	Break	Anchor	Final Appr	Est Duration	Actual	
	Economic Sum	Leaders in T	✓			2:30	0:00	4:4
B1	mit	Protesters				1:27	0:00	4:4
B2		Press confe			✓	3:29	0:00	4:4

Title Bar

Click **On Air**. A Rundown cannot be deleted while this setting is enabled.

End Date:	12/4/2008	ND Logo Each Line	
End Time:	17:16:31	Rundown Numeric Pages	
Duration:	30:00	On Air	✓
Duration based	<input checked="" type="checkbox"/>	MDS Control Active	✓
		MDS Editorial Start	2008-12-04T16:00:00

On Air Checkbox

Click **Go** at the bottom of the Rundown Properties.

Start the clock by pressing the **Space bar**. A yellow highlight bar marks the item currently being timed. Continue to press the **Space bar** as each item is passed.

5 PM News [12/04/2008 16:46]

Page	Story Slug	Segment	Break	Anchor	Final Appr	Est Duration	Actual	Front	Back	Cume	Las
B0	Economic Sum	Leaders in T	✓			2:30	0:00	4:46:31 PM	4:58:21 PM	2:30	Ma
B1	mit	Protesters				1:27	0:00	4:46:58 PM	5:00:51 PM	3:57	Ma
B2		Press confe			✓	3:29	0:00	4:48:25 PM	5:02:18 PM	7:26	Ma

The following four timers appear at the bottom of the Rundown:

How total program time compares with program duration in the Rundown properties.	Time remaining for all segments in the current story.
Over 01:15 SEGMENT: 01:00, 02:29	STORY: 01:51 PROG: 27:52
Time remaining and elapsed in the current segment.	Time remaining in the program.

Each time you press the **Space bar** the **Over/Under**, **Segment**, and **Story** clocks re-calculate from the beginning of the next segment.

- Select a line in the Rundown by clicking on it then press **Ctrl+Space bar** to move the timing bar to the line you selected.
- Press **Shift+Space bar** to move the timing bar back one line.
- Press **Alt+Space bar** to turn off timing.

The time in the lower left corner is typically based on the Estimated Time remaining, however the System Administrator may change this setting to reflect Actual Time remaining.